

# Flow Orchestration



The examples and configuration information in this topic use a model named `simpleuser` with the default endpoints generated.

The API Orchestration user interface is accessed from the APIs List page on the API Builder Console by selecting a **Flow** icon or a **Create Flow** icon for a generated or imported endpoint depending upon the current endpoint status. The API Orchestration user interface is divided into the following panels:

- Flow-node list (left side of the API Orchestration user interface) - Provides a graphical listing of the Model and Core flow-nodes. The default Core flow-node types are: Custom, Codeblock, Compose, Condition, Delay, HTTP, JSON, and Set Context. A model flow-node is displayed for each configured model and an endpoint flow-node is displayed for each imported endpoint.
- Flow editor (center of the API Orchestration user interface) - Provides a graphical space to view, edit, and create flows.
- Flow-node configuration (right side of the API Orchestration user interface) - Provides the functionality to configure the Name, Method, Parameters, and Outputs of flow-nodes.

This topic is divided into the following sections:

- [Model flow-node](#)
  - [Methods](#)
  - [Parameters](#)
  - [Outputs](#)
- [Codeblock flow-node](#)
  - [Methods](#)
  - [Parameter](#)
  - [Outputs](#)
- [Condition flow-node](#)
  - [Methods](#)
  - [Parameters](#)
  - [Outputs](#)
- [Delay flow-node](#)
  - [Method](#)
  - [Parameter](#)
  - [Output](#)
- [HTTP flow-node](#)
  - [Method](#)
  - [Parameter](#)
  - [Output](#)
- [Set Context flow-node](#)
  - [Method](#)
  - [Parameter](#)
  - [Output](#)
- [Custom flow-nodes](#)
  - [Base64 flow-node](#)
  - [Compose flow-node](#)
  - [JSON flow-node](#)

## Model flow-node

The Model flow-node methods, parameters, and outputs are described in the following sections.

### Methods

The method selections for a Model flow-node are:

- `count` - Gets a count of records.
- `create` - Creates a new model object.
- `delete` - Deletes the model object.
- `deleteAll` - Deletes all the model objects.
- `distinct` - Finds unique values using the provided field.
- `findAll` - Finds all model instances.
- `findAndModify` - Finds one model instance and modifies it.
- `findById` - Finds model instance by ID.
- `query` - Queries for particular model records.
- `update` - Updates a model instance.
- `upsert` - Creates a model record if not found, or updates the model record if found.

## Parameters

The Model flow-node parameters are described in the following sections.

### count parameters

The `count` method parameters are:

Parameter	Type	Default	Description	Configuration selection
<code>limit</code>	integer	10	The number of records to fetch.	Selector, Number
<code>order</code>	object	-	A dictionary of key-value pairs describing the field(s) for sorting. The field name is the key and the value is set to either -1 for ascending order or 1 for descending order.	Selector, Object
<code>page</code>	integer	1	Starting page number.	Selector, Number
<code>per_page</code>	integer	10	Results per page.	Selector, Number
<code>sel</code>	object	-	A dictionary of key-value pairs describing which fields to include in the query results. The field name is the key and the value is set to 1.	Selector, Object
<code>skip</code>	integer	-	The number of records to skip.	Selector, Number
<code>unsel</code>	object	-	A dictionary of key-value pairs describing which fields to exclude from the query results. The field name is the key and the value is set to 1.	Selector, Object
<code>where</code>	string	-	The JSON-encoded object specifying field constraints. The field name is the key and the value is the constraint statement or value.	Selector, String

All parameters can be enabled or disabled.

### create parameters

The `create` method parameter is:

Parameter	Type	Configuration selection
<code>data</code>	object	Selector, Object

### delete parameters

The `delete` method parameter is:

Parameter	Type	Configuration selection
<code>id</code>	any	Selector, String, Number, Boolean, Object, Array, Null

### deleteAll parameters

There are no configurable `deleteAll` method parameters.

### distinct parameters

The `distinct` method parameters are:

Parameter	Type	Default	Description	Configuration selection
<code>field</code>	string	-	The field must be distinct.	Selector, String
<code>limit</code>	integer	10	The number of records to fetch.	Selector, Number
<code>order</code>	object	-	A dictionary of key-value pairs describing the field(s) for sorting. The field name is the key and the value is set to either -1 for ascending order or 1 for descending order.	Selector, Object

page	number	1	Starting page number.	Selector, Number
per_page	integer	10	Results per page.	Selector, Number
sel	object	-	A dictionary of key-value pairs describing which fields to include in the query results. The field name is the key and the value is set to 1.	Selector, Object
skip	integer	-	The number of records to skip.	Selector, Number
unsel	object	-	A dictionary of key-value pairs describing which fields to exclude from the query results. The field name is the key and the value is set to 1.	Selector, Object
where	string	-	The JSON-encoded object specifying field constraints. The field name is the key and the value is the constraint statement or value.	Selector, String

The `limit`, `order`, `page`, `per_page`, `sel`, `skip`, `unsel`, and `where` parameters can be enabled or disabled.

## findAll parameters

There are no configurable `findAll` method parameters.

## findAndModify parameters

The `findAndModify` method parameters are:

Parameter	Type	Default	Description	Configuration selection
data	object	-	-	Selector, Object
args	object	-	Optional parameters.	Selector, Object
limit	integer	10	The number of records to fetch.	Selector, Number
order	object	-	A dictionary of key-value pairs describing the field(s) for sorting. The field name is the key and the value is set to either -1 for ascending order or 1 for descending order.	Selector, Object
page	integer	1	Starting page number.	Selector, Number
per_page	integer	10	Results per page.	Selector, Number
sel	object	-	A dictionary of key-value pairs describing which fields to include in the query results. The field name is the key and the value is set to 1.	Selector, Object
skip	integer	-	The number of records to skip.	Selector, Number
unsel	object	-	A dictionary of key-value pairs describing which fields to exclude from the query results. The field name is the key and the value is set to 1.	Selector, Object
where	string	-	The JSON-encoded object specifying field constraints. The field name is the key and the value is the constraint statement or value.	Selector, String

The `args`, `limit`, `order`, `page`, `per_page`, `sel`, `skip`, `unsel`, and `where` parameters can be enabled or disabled.

## findByID parameters

The `findByID` method parameter is:

Parameter	Type	Default	Description	JSONPath	Configuration selections
id	any	-	-	<code>\$.params.id</code>	Selector, String, Number, Boolean, Object, Array, Null

## query parameters

The `query` method parameters are:

Parameter	Type	Default	Description	Configuration selection
-----------	------	---------	-------------	-------------------------

limit	integer	10	The number of records to fetch.	Selector, Number
order	object	-	A dictionary of key-value pairs describing the field(s) for sorting. The field name is the key and the value is set to either -1 for ascending order or 1 for descending order.	Selector, Object
page	integer	-	Starting page number.	Selector, Number
per_page	integer	10	Results per page.	Selector, Number
sel	object	-	A dictionary of key-value pairs describing which fields to include in the query results. The field name is the key and the value is set to 1.	Selector, Object
skip	integer	-	The number of records to skip.	Selector, Number
unsel	object	-	A dictionary of key-value pairs describing which fields to exclude from the query results. The field name is the key and the value is set to 1.	Selector, Object
where	string	-	The JSON-encoded object specifying field constraints. The field name is the key and the value is the constraint statement or value.	Selector, String

All parameters can be enabled or disabled.

## update parameters

The `update` method parameters are:

Parameter	Type	Description	Configuration selection
data	object	Dependent on configured model fields.	Selector, Object
id	any	-	Selector, String, Number, Boolean, Object, Array, Null

## upsert parameters

The `upsert` method parameter is:

Parameter	Type	Configuration selections
data	object	Selector, Object

## Outputs

The Model flow-node outputs are described in the following sections.

### count outputs

The `count` method output is:

Output	Type	Description	Save output value as:
next	number	Successfully counted records of simpleuser.	<code>\$.count</code>

### create outputs

The `create` method output is:

Output	Type	Description	Save output value as:
next	object	Successfully created a simpleuser.	<code>\$.model</code>

### delete outputs

The `delete` method outputs are:

Output	Type	Description	Save output value as:
--------	------	-------------	-----------------------

next	object	Successfully deleted the simpleuser.	\$.delete
notfound	any	No model instance found.	-

## deleteAll outputs

The deleteAll method output is:

Output	Type	Description	Save output value as:
next	array	Successfully deleted all the simpleusers.	-

## distinct outputs

The distinct method output is:

Output	Type	Description	Save output value as:
next	array	Successfully found all unique values of simpleuser.	\$.models

## findAll outputs

The findAll method output is:

Outputs	Type	Description	Save output value as:
next	array	Successfully found all simpleusers.	\$.models

## findAndModify outputs

The findAndModify method outputs are:

Output	Type	Description	Save output value as:
next	object	Successfully found and modified simpleuser.	\$.model
notfound	any	No matching model found.	-

## findById outputs

The findById method outputs are:

Output	Type	Description	Save output value as:
next	object	Successfully found instance of simpleuser by ID.	\$.model
notfound	any	No model instance found.	-

## query outputs

The query method output is:

Output	Type	Description	Save output value as:
next	array	Successfully queried the simpleuser.	\$.models

## update outputs

The update method outputs are:

Output	Type	Description	Save output value as:
next	object	Successfully updated the simpleuser.	\$.model
notfound	any	No model instance found.	-

## upsert outputs

The `upsert` method outputs are:

Output	Type	Description	Save output value as:
update	object	Successfully updated the model.	<code>\$.model</code>
insert	object	Successfully inserted the model.	<code>\$.model</code>

## Codeblock flow-node

The Codeblock flow-node methods, parameters, and outputs for the Greet Codeblock flow-node are described in the following sections. Each method in a Codeblock flow-node corresponds to a single codeblock. The Greet Codeblock flow-node is created when a new application is created, but it can be deleted.

### Methods

The default method for the Greet Codeblock flow-node is:

- `Greet` - Some codeblock to run with the greet flow.

### Parameter

The `Greet` method parameter is:

Parameter	Type	Configuration selection
username	string	Selector, String

### Outputs

The `Greet` method outputs are:

Output	Type	Description	Save output value as:
next	string	The codeblock completed.	<code>\$.greeting</code>
error	object	The codeblock failed to complete.	<code>\$.error</code>

## Condition flow-node

The Condition flow-node methods, parameters, and outputs are described in the following sections.

### Methods

The default methods for a Condition flow-node are:

- `equals` - Tests is a value is equal.
- `exists` - Tests does a value exists, true or false.
- `greater-than` - Tests is a value is greater than another value.
- `greater-than-equal` - Tests is a value is greater than or equal to another value.
- `less-than` - Tests is a value is less than another value.
- `less-than-equal` - Tests is a value is less than or equal to another value.

### Parameters

The Condition parameters are described in the following sections.

#### `equals` parameters

The `equals` method parameters are:

Parameter	Type	Minimum length	Description	Configuration selection
-----------	------	----------------	-------------	-------------------------

source	any	1	The input to test.	Selector, String, Number, Boolean, Object, Array, Null
value	any	1	The value to test input against.	Selector, String, Number, Boolean, Object, Array, Null

## exists parameters

The `exists` method parameter is:

Parameter	Type	Minimum length	Description	Configuration selection
source	any	-	The input to test.	Selector, String, Number, Boolean, Object, Array, Null

## greater-than parameters

The `greater-than` method parameters are:

Parameter	Type	Minimum length	Description	Configuration selection
source	any	1	The input to test.	Selector, String, Number, Boolean, Object, Array, Null
value	any	1	The value to test input against.	Selector, String, Number, Boolean, Object, Array, Null

## greater-than-equal parameters

The `greater-than-equal` method parameters are:

Parameter	Type	Minimum length	Description	Configuration selection
source	any	1	The input to test.	Selector, String, Number, Boolean, Object, Array, Null
value	any	1	The value to test input against.	Selector, String, Number, Boolean, Object, Array, Null

## less-than parameters

The `less-than` method parameters are:

Parameter	Type	Minimum length	Description	Configuration selection
source	any	1	The input to test.	Selector, String, Number, Boolean, Object, Array, Null
value	any	1	The value to test input against.	Selector, String, Number, Boolean, Object, Array, Null

## less-than-equal parameters

The `less-than-equal` method parameters are:

Parameter	Type	Minimum length	Description	Configuration selection
source	any	1	The input to test.	Selector, String, Number, Boolean, Object, Array, Null
value	any	1	The value to test input against.	Selector, String, Number, Boolean, Object, Array, Null

## Outputs

The Condition flow-node outputs are described in the following sections.

### equals outputs

The `equals` method outputs are:

Output	Type	Description	Save output value as:
true	boolean	The condition tested true.	<code>\$.equals</code>
false	boolean	The condition tested false.	<code>\$.equals</code>

### exists outputs

The `exists` method outputs are:

Output	Type	Description	Save output value as:
true	boolean	The condition tested true.	<code>\$.exists</code>
false	boolean	The condition tested false.	<code>\$.exists</code>

## greater-than outputs

The `greater-than` method outputs are:

Output	Type	Description	Save output value as:
true	boolean	The condition tested true.	<code>\$.greaterThan</code>
false	boolean	The condition tested false.	<code>\$.greaterThan</code>

## greater-than-equal outputs

The `greater-than-equal` method outputs are:

Output	Type	Description	Save output value as:
true	boolean	The condition tested true.	<code>\$.greaterThanEqual</code>
false	boolean	The condition tested false.	<code>\$.greaterThanEqual</code>

## less-than outputs

The `less-than` method outputs are:

Output	Type	Description	Save output value as:
true	boolean	The condition tested true.	<code>\$.lessThan</code>
false	boolean	The condition tested false.	<code>\$.lessThan</code>

## less-than-equal outputs

The `less-than-equal` method outputs are:

Output	Type	Description	Save output value as:
true	boolean	The condition tested true.	<code>\$.lessThanEqual</code>
false	boolean	The condition tested false.	<code>\$.lessThanEqual</code>

# Delay flow-node

The Delay flow-node method, parameter, and output are described in the following sections.

## Method

The method for a Delay flow-node is:

- `delay` - Wait for a certain amount of time before continuing to the next flow-node.

## Parameter

The Delay flow-node parameter is described in the following section.

## delay parameters

The `delay` method parameter is:

---



Parameter	Type	Default	Description	Configuration selection
delay	integer	-	The length of delay, in milliseconds.	Selector, Number

## Output

The Delay flow-node output is described in the following section.

### delay outputs

The `delay` method output is:

Output	Type	Description	Save output value as:
next	integer	The delay is completed.	<code>\$.delayed</code>

## HTTP flow-node

### Method

The method for a HTTP flow-node is:

- `setHTTPResponse`

### Parameter

The HTTP flow-node parameter is described in the following section.

#### setHTTPResponse parameter

The `setHTTPResponse` method parameters are:

Parameter	Type	Minimum	Maximum	Description	Configuration selection
status	integer	100	599	-	Selector, Number
body	any	-	-	-	Selector, String, Number, Boolean, Object, Array, Null
headers	object	-	-	-	Selector, Object

The `body` and `headers` parameters can be enabled or disabled.

## Output

The HTTP flow-node output is described in the following section.

### setHTTPResponse output

The `setHTTPResponse` method does not have any configurable outputs.

## Set Context flow-node

The Set Context flow-node method, parameter, and output are described in the following sections.

### Method

The method for a Set Context flow-node is:

- `setContext`

### Parameter

The Set Context flow-node parameter is described in the following section.

## setContext parameter

The `setContext` method parameter is:

Parameter	Type	Default	Description	Configuration selection
value	any	-	-	Selector, String, Number, Boolean, Object, Array, Null

## Output

The Set Context flow-node output is described in the following section.

### setContext output

The `setContext` method output is:

Output	Type	Description	Save output value as:
next	any	-	-

## Custom flow-nodes

Custom flow-nodes which are not built into the API Builder Console can be created and installed. Axway provides three custom flow-nodes with new projects and more planned for the future. The custom flow-node handlers are created and their methods, parameters, and outputs are defined using the Axway Flow SDK. For additional information, see [Axway Flow SDK](#).

The custom flow-nodes currently provided with a new project are:

- [Base64](#)
- [Compose](#)
- [JSON](#)

## Base64 flow-node

The flow-node methods, parameters, output for the Base64 flow-node are described in the following sections. The Base64 flow-node is created when NPM installs the `nodehandler-base64` code. The Base64 flow-node is included in the default application, but it can be removed.

### Methods

The Base64 flow-node default methods are:

- `Decode` - Decodes base64 encoded data.
- `Encode` - Encodes base64 data.

### Parameters

The Base64 flow-node parameters are described in the following sections.

#### Decode parameters

The `Decode` method parameters are:

Parameter	Type	Description	Configuration selection
data	string	The data to decode.	Selector, String
as	string	Expected decoded data format.	Selector, String

The `as` parameter can be enabled or disabled.

#### Encode parameters

The `Encode` method parameter is:

Parameter	Type	Description	Configuration selection
-----------	------	-------------	-------------------------

data	any	The data to encode.	Selector, String, Number, Boolean, Object, Array, Null
------	-----	---------------------	--

## Outputs

The Base64 flow-node outputs are described in the following sections.

### Decode outputs

The `Decode` method outputs are:

Output	Type	Description	Save output value as:
Decoded	string	The base64 decoded data.	<code>\$.decoded</code>
Error	any	-	<code>\$.b64error</code>

### Encode outputs

The `Encode` method output is:

Output	Type	Description	Save output value as:
Encoded	string	The base64 encoded data.	<code>\$.b64data</code>

## Compose flow-node

The Compose flow-node methods, parameters, and outputs are described in the following sections. The Compose flow-node is created when NPM installs the `nodehandler-dot` code. The Compose flow-node is included in the default application, but it can be removed.

### Methods

The default methods for a Compose flow-node are:

- `Format object` - Compose an object by evaluating a template. The evaluated template is JSON parsed and so must be a valid JSON encoded string.
- `Format string` - Compose a string by evaluating a template.

### Parameters

The Compose flow-node parameters are described in the following sections.

#### Format object parameters

The `Format object` method parameters are:

Parameter	Type	Description	Configuration selection
data	object	The data to evaluate the template with. Use <code>\$</code> to access the entire context.	Selector, Object
template	string	The doT template.	Selector, String

#### Format string parameters

The `Format string` method parameters are:

Parameter	Type	Description	Configuration selection
data	object	The data to evaluate the template with. Use <code>\$</code> to access the entire context.	Selector, Object
template	string	The doT template.	Selector, String

## Outputs

The Compose flow-node outputs are described in the following sections.

### Format object outputs

The `Format` object method outputs are:

Output	Type	Description	Save output value as:
Next	any	-	<code>\$.value</code>
Error	any	This output is triggered if the evaluated template is not a valid JSON string. The output value is the error object.	<code>\$.error</code>

### Format string outputs

The `Format` string method outputs are:

Output	Type	Description	Save output value as:
Next	any	-	<code>\$.value</code>
Error	any	This output is triggered if the evaluated template is not valid. The output value is error object.	<code>\$.error</code>

## JSON flow-node

The JSON flow-node methods, parameters, and output are described in the following sections. The JSON flow-node is created when NPM installs the `nodehandler-json` code. The JSON flow-node is included in the default application, but it can be removed.

### Methods

The default methods for a JSON flow-node are:

- `Parse` - The parse method parses a JSON string, constructing the JavaScript value or object described by the string.
- `Stringify` - The stringify method converts a JavaScript value to a JSON string.

### Parameters

The JSON flow-node parameters are described in the following sections.

#### Parse parameters

The `Parse` method parameter is:

Parameter	Type	Description	Configuration selection
<code>json</code>	string	The JSON string to parse.	Selector, String

#### Stringify parameters

The `Stringify` method parameters are:

Parameter	Type	Description	Configuration selection
<code>value</code>	any	The value to convert to a JSON string.	Selector, String, Number, Boolean, Object, Array, Null
<code>space</code>	any	A string or number object that's used to insert white space into the output JSON string for readability purposes. If this is a number, it indicates the number of space characters to use as white space; this number is capped at 10. If this is a string, its maximum length is 10; the string is used as white space. If this parameter is not provided, no white space is used.	Selector, String, Number, Boolean, Object, Array, Null

The `space` parameter can be enabled or disabled.

## Outputs

The JSON flow-node outputs are described in the following sections.

### Parse outputs

The `Parse` method outputs are:

Output	Type	Description	Save output value as:
Next	any	-	<code>\$.value</code>
Error	any	This output is triggered if the input is not a valid JSON string. The output value is the error object.	<code>\$.error</code>

### Stringify outputs

The `Stringify` method output is:

Output	Type	Description	Save output value as:
Next	string	-	<code>\$.json</code>